

[Home](#)[Status](#)[Configure](#)[Launch Designer](#) Logged in as admin | [log out](#)**System**

- Status
- Licensing
- Backup/Restore
- Console
- User Manual

**Configuration**

- Projects
- Modules
- Gateway Settings
- Clustering

**Databases**

- Connections
- Drivers
- Store and Forward

**OPC Connections**

- Servers
- Quick Client

**OPC-UA**

- Certificates
- Settings
- Devices

**SQLTags**

- Realtime
- Historian

**Security**

- Authentication
- Auditing

**Alerting**

- Notification
- Storage
- Console

## ControlLogix 5500

**General**

Device Name	<input type="text" value="ControlLogix"/>
	Name of this device.
Browse Timeout	<input type="text" value="30000"/>
	Amount of time (in milliseconds) before a browse operation times out.
Read Timeout	<input type="text" value="30000"/>
	Amount of time (in milliseconds) before a read operation times out.
Write Timeout	<input type="text" value="30000"/>
	Amount of time (in milliseconds) before a write operation times out.
Enable Device	<input checked="" type="checkbox"/>
	Enable this device?

**Connectivity**

Hostname	<input type="text" value="192.168.1.30"/>
	The hostname or IP address the driver should try to connect to.
Communication Timeout	<input type="text" value="2000"/>
	The time in mSec to wait for a device to respond.
Browse Cache Timeout	<input type="text" value="0"/>
	How long to wait before another full browse. Set to 0 to diable automatic browsing (see manual for more information).
Slot Number	<input type="text" value="1"/>
	The slot number of the processor (Ignored if Path is used).
Connection Path	<input type="text" value="AB_VBP-1\1"/>
	The connection path to the target device (See documentation for more details).
Concurrent Requests	<input type="text" value="1"/>
	The maximum number of simultaneous requests sent to the ControlLogix at any given time.

## **Trial Version!**

We are glad you are test driving our software. Have fun. [Activate Ignition by Inductive Automation here.](#)

0:53:45

Ignition by Inductive Automation. Copyright © 2003-2010. All rights reserved. | [view license](#)